


# LMDZ Single Column Model



**LMDZ team**

LMDZ training session 2024



# Why running LMDZ in 1D (single column) mode ?

- To evaluate/develop the physical part of the model regardless of the dynamical part → central in the model development process
- To make quick sensitivity tests
- To carry out process-oriented studies
- To tune the model (see F. Hourdin's presentation)
- For teaching

.....

# LMDZ in 1D (1 column) mode physics only, no resolved dynamics

1/ Initial conditions:



# The 1D 'case' concept

A 'case' is :


- a set of initial conditions
- a set of lateral (and sometimes surface) forcings
- a time period (radiation)
- surface properties

Note that, as the large scale dynamics is prescribed through forcings, 1D 'cases' make it possible to thoroughly explore and assess the 'physics' of the model


Different 'cases' have been built - with different degrees of idealisation - to study various aspects of the physics (clouds, deep convection, boundary-layer dynamics ..)

Recent development of the so-called international standard 'DEPHY' format for 1D cases  
<https://github.com/GdR-DEPHY/DEPHY-SCM/>

# How 1D cases are built ?




Explicit simulations (LES), Grid cell, 20-100 m



« Large scale » conditions imposed

Climate model, parameterizations, « single-column » mode



Courtesy F.Hourdin

# **Available cases correspond to different meteorological situations**

## **Dry and shallow convection**

**ARMCU** (diurnal cycle of shallow cumulus over land)

**RICO** (Rain In Cumulus over Ocean,  
shallow precipitating cumulus over sea)

**AYOTTE** (convective boundary layer, sky clear )



## **Stratocumulus and transition to cumulus**

**SANDU** (transition case with 3 options : variation of SST)

**FIRE** (diurnal cycle of stratocumulus)



## **Deep convection over ocean:**

**Toga**

**case\_e** (part of Toga)

**TWPICE** : off the coast of Darwin




## **Deep convection over land:**

**Hapex** : african monsoon

**AMMA** : african monsoon

## **Idealized case:**

**eq\_rad\_conv** (RCE) : radiative  
and convection scheme active



**DICE** case : characterize boundary layer  
In the site of SGP during 3 days/nights  
May be coupled with soil model



**Cindy Dynamo** case (Madden Julian  
Oscillation study, intraseasonal  
variability in the tropical atmosphere)

.....

**GABLS4** case : interaction of a  
very stable boundary layer with a  
snow surface

**MPACE** case : mixte phase in  
Arctica. Shallow convection with  
Stratocumulus developing at the  
top of boundary layer

# How to install 1D model ?

```
cd LMDZ*****
```

```
wget
```

<http://www.lmd.jussieu.fr/~lmdz/Distrib/1D/1D.tar.gz>

```
tar xvzf 1D.tar.gz
```

```
cd 1D
```

# CAS folder

An international common format for forcings and output files has been defined.

→ <https://github.com/GdR-DEPHY/DEPHY-SCM/>

**DEPHY Cases which are up to date in CAS:** ARMCU, AYOTTE, BOMEX, DYNAMO, GABLS1, GABLS4, IHOP, ISDAC, MPACE, RICO, SANDU, SCMS

- + common forcings file is **cas.nc**
- + common output file is **hourly\_std.nc**
- + there is also histhf.nc or hourly.nc

**Other cases are in OLDCASES :**

- + forcings file is case\_name.nc or prof.inp.001
- + output file is histhf.nc or hourly.nc

# Have a look at run.sh

## Script that COMPILES the model and RUN cases

Which case(s) ?

Which physics ?

Number of levels ?


```
listecas="ARMCU/REF"
```

```
listedef="6A"
```

```
LLM="79" # imposing the number of vertical level (default 79)
# default values for various cases are defined bellow
```

```
day_step="" # number of physical steps per day
i_diag=1    # run automated post-processing scripts → plots
```

# Cases to run with different physical packages, with run.sh



# Results : in ~/1D/OUTPUT

all.pdf

ARMCUREF.pdf

**NPv6.1L79/**

RICOREF.pdf

SANDUREF.pdf

**SAVE41389/**

**~/1D/OUTPUT/6AL79/ARMCU/REF**

histhf.nc

hourly.nc


hourly\_std.nc

LES.nc


+ some pdf files

**~/1D/EXEC**

Same than OUTPUT + All the files used to run the case : forcings, .def files, listing ...



# Where are the results ? In 1D/EXEC/6AL79/ARMCU/REF




## CAUTION !

You can modify \*def files in ~LMDZ20211102.trunk/1D/EXEC/NPv6.1/ARMCU/REF and quickly rerun the model because Imdz1d.e is in this directory.


## BUT BE CAREFULL

The « original » files are either under ~/CAS or ~/INPUT  
And will be replaced at each run of run.sh



**Thank you for your attention !**

# Where are located all these cases ?



Background : low cloud cover from Calipso (Chepfer et al. 2008)