

LMDZ tutorial

Configurations, input files, forcing data

Lionel GUEZ
Olivier BOUCHER (part on aerosols)
LMD

Contents

- Configurations
- LMDZ with realistic physics
- Aqua-planet or all-land planet
- Relaxation to a 3D-temperature field

Configurations: many ways to use LMDZ

Coupling with another model

- Soil, vegetation, hydrology: Orchidée
<http://labex.ipsl.fr/orchidee>
- Ocean, sea ice, marine biogeochemistry:
Nemo
<http://www.nemo-ocean.eu>
- Tropospheric chemistry , aerosols: INCA
<http://www-lsceinca.cea.fr>
- Stratospheric chemistry: Reprobus
Marchand et al., JASTP, 2012

Configurations of LMDZ itself

- 1 or 3 dimensions
- Nudging
- Zoom
- Realistic or idealized "physical" part of the model

Use case:
LMDZ alone
3 dimensions
no nudging
realistic (terrestrial) physics

What is left to choose

- Some run-time parameters (among which concentration of greenhouse gases)
- Initial state
- Boundary (that is, surface) conditions
- Forcing atmospheric data: ozone field, fields of aerosols

Run-time parameters

- Chosen in text files which have suffix .def
- Home > Utilisateurs > Guides > LMDZ pas à pas > Utilisation comme boîte noire >
Variables des fichiers .def

Run-time parameters (continued)

- Syntax:

variable=value

Case sensitive

TRUE or FALSE for logical values

Character values without quotes

Comment lines start with #

Example: **gcm.def**

- Semantic separation of run-time parameters among six .def files

Run-time parameters (continued)

- `gcm.def`: dynamics
 - Zoom: `clon` and `clat` (center), `grossim[xy]` (zooming factor), `dzoom[xy]` (range), `tau[xy]` (steepness of transition)
- `physiq.def`: parameterizations

Run-time parameters (continued)

- config.def: level of output, coupling with other models, radiative transfer, forcing data (ozone, aerosols, greenhouse gases)
 - No ocean model: `type_ocean=force`
 - No coupling with Orchidée: `VEGET=bucket`
 - Concentration of greenhouse gases: `co2_ppm`, `ch4_ppb...`
 - Number of calls to radiative transfer procedure, per day: `nbapp_rad`

Run-time parameters (continued)

- `output.def`: fine tuning of output (choice of variables, frequency...)
- `run.def`: length of the run, dates, calendar
 - Number of days of run: `nday`
 - Starting date: `dayref` (day number in the year) and `anneeref`
 - Calendar: `calend` (character variable)

Run-time parameters (continued)

- **traceur.def**: tracers
 - Special syntax
 - 1st line: number of tracers
 - Then one line per tracer, with a number identifying the advection scheme
 - For more information on available advection schemes: infotrac.F90


Initial state and boundary conditions

- Separate program: ce0l
- Distributed with the program gcm, compiled with the same tools
- Home → Utilisateurs → Guides → LMDZ pas à pas → **Utilisation comme boîte noire**
- Run ce0l with the same .def files than those you want for gcm
Exception: calendar

Initial state and boundary conditions (continued)

- ce0l creates 2 files for initial state:
start.nc for the dynamics part of gcm
startphy.nc for the physics part of gcm
- ce0l creates 1 file for 1 year of boundary conditions:
limit.nc

Initial state and boundary conditions (continued)



Calendar

- Calendar is used in ce0l to create boundary conditions
- For years with constant length, 360 or 365 days:

`calend=earth_360d`

or

`calend=earth_365d`

Same value for ce0l and gcm


Calendar (continued)

- For the real calendar (with leap-years):
 - Run ce0l for each year you want boundary conditions for:
calend=gregorian
anneeref=<the right year>
 - For gcm: calend=earth_366d

Ozone

- Run-time parameter in config.def:
`read_climoz=0, 1 or 2`
- 0: analytic expression for the ozone field (see ozonecm_m.F90)
- 1: read day-night average of ozone field from a file
- 2: also read daylight average from the same file (good idea if there are a few model layers in the mesosphere)

Ozone (continued)



Aerosols: running without INCA

- Reminder: for LMDZ – INCA version with interactive aerosols, management of radiative transfer is different
- LMDZ without INCA:
run-time parameter in config.def
aerosol_couple = FALSE

Nature of aerosols

Run-time parameter in config.def

flag_aerosol (integer):

- 0: no aerosol
- 1: sulfate
- 2: black carbon
- 3: particulate organic matter
- 4: marine salts
- 5: dust
- 6: all

Aerosols: input files

- If $\text{flag_aerosol} > 0$:
gcm reads aerosol data from files
`aerosols.nat.nc`
[+ another file, depending on `aer_type`]

Aerosols: input files (continued)

- Run-time parameter `aer_type` (character variable) in config.def:
 - `preind`: pre-industrial aerosols → `aerosols.nat.nc` only
 - `actuel`: when you want to use a climatology of anthropogenic aerosols → `aerosols.nat.nc` + `aerosols1980.nc` (fixed name, meaningless)
 - `annuel`: `aerosols.nat.nc` + `aerosolsYYYY.nc` where `YYYY` is the current year

Aerosols: input files (continued)

- Input files should contain concentrations of aerosols of all the desired types (according to flag_aerosol)
- Input files should already be horizontally regridded to the gcm grid

Aerosols: direct and indirect effects

- Run-time parameters `ok_ade` and `ok_aie` (logical) in config.def to activate direct and indirect effects of anthropogenic aerosols
- If `ok_ade = FALSE` then direct effect of natural aerosols only
If `ok_aie = FALSE` then indirect effect of natural aerosols only

Aerosols: direct and indirect effects (continued)

- You can choose `ok_ade` and `ok_aie` independently
- `flag_aerosol` must be ≥ 1 if `ok_ade` or `ok_aie` is TRUE
- If `ok_ade` or `ok_aie` is TRUE then corresponding diagnostics are output (in particular variables to compute radiative forcings, `topswad` ou `topswai`)



Stratospheric aerosols

- Run-time parameter `flag_aerosol_strat` (logical) in config.def, independent of other aerosol flags
- If TRUE, gcm reads 3D aerosol input data from files with monthly timestep
- Input data are available over period 1850 to 2010
- An IDL script prepares input file for various model resolutions

Aerosols for expert users

- Run-time parameter `new_aod` (logical): to use the most recent parameterization of aerosol optical depth.
TRUE is the default value.
Note: `new_aod=FALSE` can only be used with `flag_aerosol=1` (sulfate aerosols only).

Aerosols for expert users (continued)

- Run-time parameters in config.def:

$\text{bl95_b0}=1.7$

$\text{bl95_b1}=0.2$

(recommended values)


Link cloud droplet number concentration to aerosol mass concentration

(Boucher and Lohmann, 1995)


Aerosols for expert users (continued)

- If you want to compute at each time step the direct or indirect effect that aerosols would have, but not let those effects impact the simulation:
 - Set the variable `aerosolfeedback_active` to `.false.` in procedure `sw_aeroAR4.F90`
 - Recompile the program
 - Choose `flag_aerosol > 0` and `ok_ade = TRUE` or `ok_aie = TRUE` at run-time

Putting it all together



Chaining one-month runs



Where do you get the input files ?

Run-time parameters

Template .def files are distributed with LMDZ source files

- Directory **DefLists**
- physiq.def_L39_AR40.0: 39 levels, physics used for AR4, old physics
- physiq.def_L39_NPv3.2: new physics

Initial state and boundary conditions

NetCDF files required by ce0l are in:

- http://www.lmd.jussieu.fr/~lmdz/LMDZ_Init
- DODS server
<http://dods.extra.cea.fr/work/p86ipsl/IGCM/STORAGE/INIT/ATM>

Forcing data for CMIP 5

- A lot of data, for pre-industrial, historical or future simulations (with different scenarios)
- NetCDF files are stored at the national supercomputing centers, IDRIS and CCRT, so you need to find access to them

Forcing data for CMIP 5: ozone

- `gaya:~rpsl035/IGCM/INIT/ATM/LMDZ/Ozone/HYBRIDE/v2.clim/tro3_{year}.new.nc`
- **Wiki**
`http://forge.ipsl.jussieu.fr/igcmg/wiki/InfosOzone`

Forcing data for CMIP 5: aerosols

- `gaya:~rpsl035/IGCM/BC/ATM/LMDZ/LMD9695/AR5/HISTORIQUE/aerosols_11YearsClim_{year}v5.nc`
- Each file contains all aerosol types.
- **Wiki**
`http://forge.ipsl.jussieu.fr/igcmg/wiki/InfosAerosol`

Aqua-planet or all-land-planet

Definition

- Zero relief
- Only one type of surface globally : either land or ocean
- Surface temperature is:
 - forced for an aqua-planet
 - computed for a land-planet (we still have to choose an initial field)

Selecting the aqua- or land-planet

- Run-time parameter `iflag_phys` (integer) in `gcm.def`
Choose $\text{iflag_phys} \geq 100$ (instead of default value 1 for Earth surface, full physics)
- $\text{iflag_phys} = 101$ to 114 : aqua-planet
 $\text{iflag_phys} = 201$ to 214 : land-planet
Different T_s fields, constant for aqua-planet,
initial value only for land-planet

Selecting the aqua- or land-planet (continued)

- See (analytic) definition of the 14 T_s fields in procedure `profil_sst`

Initial state and boundary conditions

- You do not go through the ce0l step
 - Set run-time parameter `read_start` to FALSE in `gcm.def`
`gcm` creates an initial state
 - `gcm` also creates a file `limit.nc` for boundary conditions
- `gcm` creates `restart.nc` and `restartphy.nc` so switch `read_start` to TRUE for the next run

Forcing data

It may be a good idea to use adapted ozone and aerosol fields, symmetrical about the equator

Idealized physics: relaxation to a given
3-dimensional temperature field

Selecting temperature relaxation

Set run-time parameter `iflag_phys=2` in `gcm.def`

- Analytic definition of the 3D equilibrium temperature field
- Damping of low-level wind to represent boundary-layer friction
- From Held and Suarez (1994)
- Some run-time tuning parameters (relaxation time...), see `inicademic.F90`

Initial state, no boundary condition

- You do not go through the ce0l step
 - Set run-time parameter `read_start` to FALSE in `gcm.def`
`gcm` creates an initial state
 - No file `limit.nc`
- `gcm` creates `restart.nc` and `restartphy.nc` so switch `read_start` to TRUE for the next run

Note

- No other forcing data
- You do not use physiq.def, config.def nor output.def
- You can bypass compilation of physics files with option -p nophys of makelmdz → much quicker compilation